


IncrediMail Help Center




Q: How do I add a new email account in IncrediMail?

A: Adding a new email account in IncrediMail is simple. To configure your new email account settings, just follow these steps:

1. In the IncrediMail main window, click the **'Tools'** menu (marked in red) and select **'Email Accounts...'** (marked in blue).



2. At this point, the 'Mail Accounts' dialog opens. Click **'Add'** (marked in red) to add a new email account.




1. At this point, the 'Account Wizard' dialog opens.

Manually configuring the Email Account

To manually configure your email account settings in IncrediMail. Please follow these steps:

1. Enter your Display name (your name, as you would like it to appear to your email recipients) and your email address into the appropriate fields (marked in red), and click **'Next'** (marked in blue).

 **Account Wizard**

Name and email address


Please enter your name, just as you would like it to appear in the emails you send.

Your name is:
 For example: Bart Simpson

Please enter your email address. Your email address is the address other people use to send email messages to you.

Your email address:
 For example: paul@isp.com

2. If you are connected to the Internet, IncrediMail attempts to fill out the email account server settings automatically, as shown in the image below. If you are not connected to the Internet, either connect or click '**Skip**' and enter your incoming and outgoing mail servers manually.

 **Account Wizard**

Online search for your server settings...

Please sit back and relax while IncrediMail attempts to automatically fill out the email server settings for you, using the email address that you provided.
 This process may take a moment or two.

If successful, the settings will be filled in on the next page.

If you prefer to fill out the server settings manually, please press "Skip" below at any time.

3. Select your incoming mail server type, POP3 (marked in red), enter your incoming mail server (pop.secureserver.net) and outgoing mail servers (smtpout.securserver.net) (marked in blue) and

click **'Next'** (marked in green).

Note: Your email server settings are provided by your email account provider.



Note: IncrediMail does not support IMAP folders synchronization at the moment, however you can leave copies of messages on the server, this way incoming messages are downloaded to all your email accounts and computers.

4. Enter your email account username (your complete e-mail address) and password (supplied by your Internet Service Provider) (marked in red) and click **'Finish'** (marked in blue).



5. Click **'OK'** to close the 'Account Wizard' dialog and you can start using your newly configured email account.
6. After setting up your new account. Click on "Tools" then "Email Accounts" select your new account.
7. Select "Properties" then select "Servers". Find "Outgoing Port" and change it to "80".
8. Then select "Apply" and "Close".
9. That should complete your set up.